




Ambarella

A12 Image DSP Pipeline

06/01/2016

V 1.0

A12 Image Pipeline Block Diagram



Static Bad Pixel Correction



- 1-bit per pixel “static bad pixel stream” indicates the good/bad status of pixels coming from the sensor.
- Correction applied as long as one or more same-color neighbors (out of the 8 available) is good.
- Correction is directionally oriented if enough neighboring pixels indicate directional structure.
- Otherwise correction is an average of the available good neighbors.

Dynamic Bad Pixel Processing

- Bad pixel detection is based on looking for the rank-ordered minimum and maximum outliers in neighborhood pixels same Bayer color.
- 1st order and 2nd order detection supported (based on expected amount of bad pixel clustering).
- 1st order detection can detect isolated pixel outliers.
- 2nd order detection can detect clusters-of-two pixel outliers.
- Independent dark and bright settings

Dynamic Bad Pixel Processing



- Correct pixels that is very different from their eight closest same color neighboring pixels in CFA domain

idsp_dbp_correction_t

***bad_corr**

u8 enable

0: disable
1: hot 1st order, dark 2nd order
2: hot 2nd order, dark 1st order
3: hot 2nd order, dark 2nd order
4: hot 1st order, dark 1st order

u8 hot_pixel_streng
 th

Hot pixel correction strength, 0-10

u8 dark_pixel_stren
 gth

Dark pixel correction strength 0-10

u8 correction_mode

0: normal correction mode
1: aggressive correction mode:
may be useful in extremely
noisy situations.


CFA-domain Noise Filter



- ◆ Adaptively filters center pixel with neighbor pixels
- ◆ Separate controls for fine and coarse filtering
- ◆ Programmable R/G/B center weights for stronger / weaker filter

Confidential
For PROTRUST Only

CFA-domain Noise Filter Block



CFA-domain Noise Filter



- ◆ There are two filters, the one is normal and the other is fine
- ◆ The two filters will run at the same time, but only one filter output will be chosen.
- ◆ Mostly the normal filter output will be chosen. The noise level R/G/B is the threshold of normal filter
- ◆ The fine detail's noise level is decided by 'noise_level_RGB' and 'Strength_Fine_RGB'. If "Strength_Fine R/G/B = 0", then fine detail's noise level threshold is the same as normal noise level R/G/B threshold. If "Strength_Fine R/G/B" = 256, then the fine detail's noise level threshold will be about 10 times than normal noise level R/G/B

CFA-domain Noise Filter



- ◆ The extent regular R/G/B decides two things:
 - ◆ How large the area to find the match. If the value is 30, then it is 7x7 for R/B, 5x5 for G.
 - ◆ How many pixels within the match to judge it is successful to the filter output. The larger the number is, the more matching pixels are required
- ◆ Selectivity means the weighting of matching pixels for filtering
- ◆ The larger value of Selectivity means the stronger weighting in closer pixels. The value 0 means all the pixels are equal weighting.


CFA-domain Noise Filter



- ◆ The overall flow is
 - ◆ To judge if there is enough matching at the normal CFA filter output. If yes, then fine detail filter result won't be taken
 - ◆ If there is not enough matching at the normal coarse CFA filter output, then it will go to fine detail filter output.

Confidential
For PROTECT ONLY

GbGr mismatch filter



GbGr mismatch filter

- ◆ Switch between correct (average with diagonal neighbors) and CFA noise filter
- ◆ GbGr correct if pass narrow test (close neighbors show mismatch) or wide (wide area shows mismatch)
- ◆ Narrow detection is just enable / disable

GbGr mismatch filter wide test



◆ Parameters:


gb_gr_mismatch_correct.narrow_enable	0-1
gb_gr_mismatch_correct.wide_enable	0-1
gb_gr_mismatch_correct.wide_thresh	0-256
gb_gr_mismatch_correct.wide_safety	0-256

- ◆ Wide detection passes is both of the following are true:
 - ◆ A measure of mismatch is greater than wide_thresh (so increasing wide thresh make the filter weaker)
 - ◆ A measure of how likely systemic mismatch is caused by true signal (i.e., Gbs should be higher or lower than Grs) is less than wide_safety (so increasing wide_saftey make the filter stronger)

Color Correction



- ◆ 3D correction “replaces” traditional matrix and gamma curves, allows for arbitrary correction
 - Output tables can be used for “real time” modifications (like RGB auto-knee).
 - Tools exist for programming based on color matrix and gamma curves and camera matching
 - Camera matching can be region-based
 - Tools exist for taking in arbitrary mapping (spreadsheet), programming A7 registers
 - Soft gamut clipping possible (color matrix uses hard clip)



Chroma noise filter

- ◆ Same structure as CFA noise filter, but works on chroma samples

Confidential
For PROTRULY Only

Chroma noise filter

- Noise_level
 - Increasing noise level increases filtering strength.
- Radius
 - Determine the spatial extent of the filter
 - Extent_fine (below) are increases as radius is increased.
 - Increasing radius increases filtering strength.
- Extent_fine
 - Determines the size of the filter support region.


Luma spatial filtering and sharpening




- ◆ Flexible hardware
- ◆ Single pass can do spatial noise filtering (directional) and sharpening (video)

Confidential Only
For PROTRULY

Luma spatial filtering and sharpening



Mode 0



Mode 2

Mode 0 and Mode 2

- ◆ See diagram on previous page. When sharpening is performed it is performed in conjunction with a spatial filter, which can either come before sharpening (mode 0) or work in parallel with it (mode 2).
- ◆ As in mode 0, the spatial filtering FIR is controlled by the `sharpening_spatial_filter.fir*` parameters.
- ◆ Level strength adjust is similar the same named parameters (`*level_str_adjust_*`) in advanced spatial filter, except that the max strength is 16 (not 64).

FIR



- ◆ Used in noise reduction and sharpening
- ◆ Supports isotropic and 8-directional FIR
- ◆ For sharpening and spatial filter FIRs, we decide to use directional or isotropic based on edge threshold

FIR Parameters

- ◆ When directional is chosen, the FIR coefficients are selected based on one of 8 chosen edge directions.
- ◆ The table below lists the parameters for a single FIR. All parameters except the last two are used to specify the FIR coefficients. In S2, edge_thresh and wide_edge_detect are often specified filter (e.g., sharpening) rather than per FIR.

Parameter	Number	Range
fir specify	1	[0, 4]
fir strength iso	1	192 for 5x5, 256 for 7x7
fir strength dir	1	
fir per dir fir iso strength	9	
fir per dir fir dir strength	9	[0, 256]
fir per dir fir dir amounts	9	
fir coefs	variable	[-256, 256]
fir edge thresh	1	[0-2047]
fir wide edge detect	1	[0, 8]

Fir_specify



- ◆ The table below lists the options for “fir_specify”, when option 1 or 4 is used, the user specifies the “fir_coefs” array contains the number of unique coefficients needed to fill in all FIRs

fir_specify	Directions	params used	Description
0	ISO only	fir_strength_iso	Single strength determines FIR size
1	ISO only	fir_coefs	Only isotropic but fully manual
2	ISO + dir	fir_strength_iso fir_strength_dir	One strength for isotropic, one for directional.
3	ISO + dir	fir_per_dir_fir_iso_strengths fir_per_dir_fir_dir_strengths fir_per_dir_fir_dir_amounts	For each direction, the user specifies an isotropic strength, a directional strength, and amount to blend isotropic and directional
4	ISO + dir	fir_coefs	Fully manual

Fir_specify (cont.)



- The charts below show the placement of the coefficients


fir_specify	FIR size	number of coefficients
1	7x7	10
4	7x7	9 (directions) *25

Option 1, 7x7							Option 4, 7x7								
0	1	2	3	2	1	0	0	1	2	3	4	5	6		
1	4	5	6	5	4	1	7	8	9	10	11	12	13		
2	5	7	8	7	5	2	14	15	16	17	18	19	20		
3	6	8	9	8	6	3	21	22	23	24	25	26	27		
2	5	7	8	7	5	2	20	19	18	17	16	15	14		
1	4	5	6	5	4	1	13	12	11	10	9	8	7		
0	1	2	3	2	1	0	6	5	4	3	2	1	0		

Fir_specify (cont. 2)



- ◆ For option 4, 25 coefficients are provided per edge, direction 0 is isotropic; the other 8 directions are show below:



Fir_specify (cont. 3)

- ◆ For option 0, 2 and 3, the FIRs used are interpolated from predefined FIRs. The FIRs are defined for strengths of 0, 64, 192 and 256
- ◆ For option 0, only the predefined isotropic (direction 0) FIRs are used.
- ◆ For option 2, each direction (0 ... 8) is interpolated based on the strength; direction 0 (isotropic) uses `fir_strength_iso` and directions 1-8 all use `fir_strength_dir`.

Fir_specify (cont. 4)

- ◆ For option 3, the fir for direction “dir” is computed as follows:
 - A. `fir_per_dir_fir_dir_strengths[dir]` is used to interpolate a directional FIR with direction “dir”
 - B. `fir_per_dir_fir_iso_strengths[dir]` is used to interpolate an isotropic FIR
 - C. To define $W = \text{fir_per_dir_fir_dir_amounts}[\text{dir}] / 256$
Then $[W \times \text{the result of “A”}] + [(1-W) \times \text{the result of B}]$ is the final FIR used

FIR edge

- ◆ `fir_edge_thresh` is the threshold used to determine if a directional or isotropic FIR is used.
- ◆ `fir_wide_edge_detect` is used to determine how wide of an area to use when determining an edge direction; the higher the value, the wider the area used.

Confidential Only
For PROTRUCK only

Sharpening FIR

- ◆ User specifies 10 unique parameters, all others are inferred by symmetry
- ◆ FIRs should sum to 0
- ◆ Taps are specified in units of 1/256, with units as shown below

0	1	2	3	2	1	0			Coefficient	Bits	Range
1	4	5	6	5	4	1		9	9		[-256, 255]
2	5	7	8	7	5	2		8	8		[-128, 127]
3	6	8	9	8	6	3		7	7		[-64, 63]
2	5	7	8	7	5	2		4-6	6		[-32, 31]
1	4	5	6	5	4	1		0-3	5		[-16, 15]
0	1	2	3	2	1	0					

“low-pass”

- ◆ Center pixel minus FIR is added to final output.
- ◆ FIR is a high-pass filter, center pixel minus FIR is a low-pass filter. So “low-pass” can be viewed as the unsharp mask in unsharp masking, with FIR programmed as inverse of unsharp mask
- ◆ Based on coring table programming and level control, sharpening can be used for sharpening, noise reduction, or both

Coring Tables

- ◆ The output of the FIR is applied to the coring table to get the coring multiplier. The multiplier is then multiplied by the FIR output
- ◆ There are 256 entries in the coring table to cover the full range of FIR outputs, with negative and positive outputs treated separately. Interpolation is used between entries
 - 0: Smallest FIR output (i.e., largest negative value)
 - 128: FIR output = 0
 - 255: Largest positive FIR output


Coring Tables (continue)

- ◆ Coring table entries
 - A multiplier of 1 → FIR output is passed unchanged.
 - A multiplier of >1 → FIR output is increased. This will cause sharpening.
 - A multiplier of <1 → FIR output is decreased. This will cause noise reduction.
 - Unit is 8

Level Controls

- ◆ The way coring multiplier computations are modified based on “level” as follows:
 - a. `sharpening_coring_index_scale.*` scales the index way from the center. Strengths < 16 move the index toward the center (entry 128) and strength > 16 move the index away from the center.
 - b. The coring multiplier is multiplied based on the result of `sharpening_scale_coring.*`.
 - c. The minimum coring multiplier is the result of `sharpening_min_coring_result.*`/8 (i.e., the strengths here have three more fractional bits than the coring table entries.)



Level Controls (continue)



Coring Index Scale Level Controls





sharpening_level_overall




Coring Scale Level Controls



sharpening_level_overall




Minimum Sharpness Level Controls



Sharpening and Maximum Change



Applying sharpening



Video MCTF




◆ Parameters:

Type	Field	Description
UINT8	Enable	0: Disable Mctf function 1: Enable Mctf function
UINT16	YMaxChange	0-255. Larger value means stronger filter
UINT16	UMaxChange	0-255. Larger value means stronger filter
UINT16	VMaxChange	0-255. Larger value means stronger filter
UINT8	WeightingBasedOnLocalMotion	0:Disable Temporal Adjust 1:Enable Temporal Adjust
UINT8	Threshold[4]	0-63. Larger value means stronger filter
UINT8	Threshold1[4]	0-63. Larger value means stronger filter
UINT8	Threshold2[4]	0-63. Larger value means stronger filter.
UINT8	Threshold3[4]	0-63. Larger value means stronger filter
UINT16	Alpha1[4]	0-255. Smaller value means stronger filter
UINT16	Alpha2[4]	0-255. Smaller value means stronger filter
UINT16	Alpha3[4]	0-255. Smaller value means stronger filter

Video MCTF - Temporal control chart



- ◆ When Temporal Adjust disable, Threshold/Alpha[0-2], control Y, Cb and Cr channel, Threshold/Alpha[3] is invalid.
- ◆ When Temporal Adjust enabled, Threshold/Alpha[0-3] are used for different motion score, Y, Cb and Cr share same parameters.



MCTF Temporal controls

- ◆ Each sample is combined with a sample from the previous picture in a three-step process.
- ◆ In step 1, a weight W is computed using the following parameters:
 - **T0-T3**
 - **Alpha0 - Alpha3**
- ◆ In step 2, a preliminary filtered sample is computed as:
 - $$\text{preliminary} = ((255 - W) * \text{previous} + W * \text{current}) / 255$$
- In step 3, the final filtered sample is computed as the preliminary filtered sample, but with change from the current sample limited to **maxchange**.